

---

### Version 1.2.6 (Released 2020-04-01)

---

1. Fixed the connection problem when APP jumps to IAP in HID communication mode.

---

### Version 1.2.5 (Released 2019-10-29)

---

1. Added the "Baud Rate" option.
2. Added the function of automatically saving and recording parameters.

---

### Version 1.2.4 (Released 2019-10-08)

---

1. "App Start Address" was changed to be input directly.

---

### Version 1.2.3 (Released 2019-05-14)

---

1. Automatically clear the receive buffer before sending serial ports.

---

### Version 1.2.2 (Released 2018-12-17)

---

1. When opening the APP to download file, the APP Start Address will no longer refreshed as the first option.

---

### Version 1.2.1 (Released 2018-10-29)

---

1. Add the feature of automatic enumeration of USB devices and serial ports.

---

### Version 1.2.0 (Released 2018-10-15)

---

1. Added the feature of downloading SPIF program through IAP.

---

### Version 1.1.1 (Released 2018-9-18)

---

1. Added the 0x08020000, 0x08040000 and 0x08080000 in the "App Start Address"

---

### Version 1.1.0 (Released 2018-7-9)

---

1. Added the USB-HID communication mode.
2. In USB communication mode, added the feature "CRC verify after download".
3. In USB communication mode, added the judgment of APP download address, if it is different from the APP address in IAP, an error message will be displayed.

## Version 1.0.0 (Released 2018-5-8)

---

Initial release.